MICROCOM CORPORATION 315M THERMAL KIOSK PRINTER


SETUP GUIDE

FOR WINDOWS APPLICATIONS

REVISION 1.0.1 • LAST UPDATED 09/01/2020 • PN 880078-0100 © COPYRIGHT 2020 BY MICROCOM CORPORATION • ALL RIGHTS RESERVED



HARDWARE OVERVIEW



- 1. Feed/Cut Button
- 2. Error LED
- 3. Power LED
- 4. Low Paper Sensor Input
- 5. Adjustable Paper Guides
- 6. USB Port
- 7. Power Input
- 8. Top Cover Release
- 9. Paper Feeding Arm

Feed/Cut Button Operation

- **Press and hold:** Feed paper through the printer manually.
- Double-Tap: Activate cutter.

Printing a Test Form


While paper is loaded, **hold** the **Feed/Cut** button while **powering on the printer.** This will print and cut a self-test form with detailed information on the printer's configuration and usage history.

WINDOWS DRIVER INSTALLATION

Download the Windows Driver

Download the Windows Driver from the 315M product page:

https://www.microcomcorp.com/products/315m/



Windows Driver Installation

Plug the printer into the PC and power it on. Once the driver package has finished downloading, extract the archive and launch **Setup.exe** to begin installation.

Read and accept the legal agreement and then click Next.




315M legal agreement

At the **Select Install Module** menu, verify that **Microcom 315M** is selected in the **Embedded** dropdown menu and click **Next**. You may also optionally choose to set the 315M as the default printer.

碞 Printer Driver Setup					
	-Select Install Mo	dule			
	C Receipt		· ·		
1016	C Ticket		<u>_</u>		
0)	C Label		~		
	© Embedded	Microcom 315M	•		
17th	☐ Set As Default Printer				
Press''F1''for help	< <back(<u>B)</back(<u>	Next (N)>> Ca	ncel (<u>C</u>)		

Make sure Microcom 315M is selected

At the Setup Type menu, select Typical and click Next.



Set up the driver as a **Typical** installation

Verify that printer is plugged in and powered on. At the **Set Printer Port** screen, select the **USB_Microcom 315M_1** listing and click **Install** to finalize installation.

🛃 Printer Driver Setup		- 🗆 🗡	<
	Set Printer Port Ports: COM port settin Baud Rate: Byte Size: Protocol: IP:	USB_Microcom 315M_1 • g • 38400 • Parity: None 8 • Stop Bits: 1 Hardware •	
Press''F1''for help	< <back(<u>B)</back(<u>	Install (] Cancel (<u>C</u>)	

Select the USB_Microcom 315M_1 listing

WINDOWS DRIVER SETTINGS OVERVIEW

Configure the driver by navigating to the **Devices and Printers** menu, right-clicking the **Microcom 315(U) 1** listing, and selecting **Printing Preferences**.

Layout Tab

- **Orientation:** Set the printer to print in either **Portrait** or **Landscape** orientation.
- Advanced: Access advanced printer configuration options.

🖶 Microcom 315M(U	l) 1 Print	ing Preferenc	:es		×
Layout Paper/Quality	Main	Water Mark	Operation	Version	
Orientation:					
A Portrait		~			
				=	
				Ad <u>v</u> anced	
			E	OK Cancel <u>Apply</u>	

Layout tab of the Printing Preferences menu

Paper/Quality Tab

- Paper Source: Set the printer to use Roll or Black Mark paper.
- **Media:** Adjust the time the presenter will hold a printout after being printed.
- Advanced: Access advanced printer configuration options.

🖶 Microcom 315M(U) 1	Printing Preferences	×
Layout Paper/Quality M	Main Water Mark Operation Version	
Tray Selection		
Paper <u>S</u> ource:	Automatically Select ~	
Media:	Presenter Wait 2 Sec 🗸]
		_
	Ad <u>v</u> anced.	
	OK Cancel Ap	ply

Paper/Quality tab of the Printing Preferences menu

Main Tab

- **Paper Size:** Adjust the maximum paper size the printer will print before cutting.
 - Note: To define a custom form size, highlight any printer in the Devices and Printers menu and select Print Server Properties in the top menu. In the Printer Server Properties menu, check Create a new form in the Forms tab to define a new paper size.
 - Note: The maximum supported paper width for the 315M is 3.17".
- **Print all text as graphics image:** If a document contains text, it will first be rasterized into a graphic image before being printed. It is recommended to keep this set to **No.**

🖶 Microcom 315M(U) 1 Printing Preferences	×
Layout Paper/Quality Main Water Mark Operation Version	
Document Setting	
Paper Size: 80 x 203mm V	
Print all text as graphics image: O Yes No	
OK Cancel	Apply

Main tab of the Printing Preferences menu

Water Mark Tab

- **No Water Mark:** No water mark will be present on printouts.
- **Image Water Mark:** A water mark will be overlaid on printouts. This water mark is sourced from a bitmap image.
- Text Water Mark: A plain text water mark will be overlaid on printouts.

🚔 Microcom 315M(U) 1 Printing Preferences	×
Layout Paper/Quality Main Water Mark Operation Version	
No Water Mark Image Water Mark Bitmap: Browse	
Text Water Mark Text: CONFIDENTIAL Font Type: Arial Font Style: Regular Font Size: Angle: 45 Print Position: Center-Middle Size: 50 50	
OK Cancel <u>Appl</u>	/

Water Mark tab of the Printing Preferences menu

Operation Tab

- **Start of Document:** Set a custom command to trigger at the beginning of every print job.
- **Start of Page:** Set a custom command to trigger at the beginning of every page in a print job.
- **End of Page:** Set a custom command to trigger at the end of every page in a print job.
- End of Document: Set a custom command to trigger at the end of every print job.

📥 Mici	rocom 315M(U) 1 Print	ing Preferen	ces			×
Layout	Paper/Quality	Main	Water Mark	Operation	Version		
St	art of Document	Oper	ation when do	cument starts	1		
	Start of Page	Oper	ation when pag	ge starts			
	End of Page	Oper	ation when pa	ge ends			
E	nd of Document	Oper	ation when do	cument ends			
				L	ОК	Cancel	Apply

Operation tab of the Printing Preferences menu